How to Build a Simple Stateflow Model


Jim Freudenberg Jeff Cook EECS 461

Introduction

- These slides will show you how to build a simple Stateflow model using Matlab release 2018a.
- This is the version of Matlab we use in the lab.


Power Switch Simulink Model

• Simulink model of a power switch that toggles on and off at the zero crossings of a sine wave




Inside the State Chart

- Two states of the power switch: on and off
- Transitions between the states happen whenever the event "Switch" occurs
- By default, the initial state is "off"




Running the Simulation

- Open the scope by clicking on it
- Run the simulation by selecting "run" from the simulation menu, or by clicking the green arrow
- There are many scope options available from the pull-down menus that allow you to zoom in or out, log data, change the color and line width, etc.




Create Simulink Model

- Launch Simulink
- Create a Blank Model from the Simulink Start Page
- Open the Library Browser from the View menu
- Save the model with a name like "my_switch"
- Near the bottom of the Library Browser you will find Stateflow. Select it and the Stateflow block set will appear on the right side of the browser




Add Statechart to Simulink Model




Adding States to a Statechart

- Open statechart "on_off" by double clicking
- Drag two states from the menu on the left side of the chart into the model
- The first will have an arrow entering it. Place it on the lower right.
- Name the states "Power_on" and "Power_off" by editing the "?" in the upper left corner
- To delete a state, just select it and hit "delete"



Creating Transitions between States


- To create a transition between states, hold the cursor over the border of the starting state – it will turn into crosshairs
- Hold down the mouse button and drag the mouse to the terminal state – this will create a transition (denoted by an arrow) connecting the states
- Click on the transition and replace the resulting "?" with the name of the event that causes the transition. In this example, we'll call our event "Switch"*



* Lower case "switch" is a reserved word in Stateflow and will cause an error. Be sure to call it upper case "Switch" or a different name!

The Default Transition


- The arrow entering the first state added to the chart indicates the initial transition, or initial state.
- The initial state may be changed by clicking on the arrow and hitting delete.
- A new default transition may be added by dragging the arrow icon from the menu to the border of the desired initial state



Adding an Event

- From the "Chart" pull-down menu, select "Add Inputs and Outputs" and then "Event Input from Simulink"
- A window will open allowing you to name the event ("Switch"), and to specify that the event triggers on the rising edge of the sine wave
- You may get an error message warning you to fix an initialization problem. Be sure to do so!

File Edit View Display	Stateflow (chart) my_switch/on_off Chart Simulation Analysis Code Tool:	s Help		
▶ • • • • ♦	Parse Chart	▶ • > ⊘ - #		
on_off	Group & Subchart			
 ● my_switch ▶ □ on_ 	Add Inputs & Outputs > Add Other Elements >	Data Input From Simulink Data Output To Simulink		
Power_on	Add Pattern In Chart Insert Pattern On Selection Save Pattern	Event Input From Simulink Event Output To Simulink		
,oř	Create Container	Message Input From Simulink Message Output To Simulink		
*	Format Arrange			
	Library Link			
la ▶_	Decomposition Execution Order			
	Subchart Mappings Properties			
Ready	125%	VariableStepAut		




Open the Model Explorer

- Navigate to the Model Explorer by selecting from the "View" menu
- The Model Explorer lets you edit the event you have just defined and add new events
- The Model Explorer is shown on the next page

	•	Stateflow (ch	art) my_s	witch/on_off
File	Edit	View Display Chart Simulation	Analysis	Code Tools Help
>	-		<mark>ዕ</mark> <mark>೫</mark> L	<u>> ⊿⊓ ○ □▷ - >> ⊘ - </u>
- C	-	Model Explorer		Model Explorer ^H
on_o	off	Simulink Project Model Dependency Viewer		Base Workspace
•	<mark>™</mark> my_			Data Dictionary
Đ,		Requirements at This Level Model Browser	•	Model Workspace
K K K	F	Property Inspector Symbols	☆第Ⅰ	
		Viewmarks	•	
, v v v v v v v v v v v v v	Ĺ	Configure Toolbars ✓ Toolbars ✓ Status Bar ✓ Explorer Bar	Power	_off
\$.		Navigate Zoom	*	
fx		✓ Smart Guides		
		MATLAB Desktop		
Ready	1			125% VariableStepAuto


The Model Explorer



- Note the event is named Switch, it is triggered on Rising edges, and the Execute Chart at Initialization box is checked.
- If there were multiple events, they would each have a different Port number

Adding the Sine Input

- Return to the top-level Simulink Diagram
- The statechart "on_off" now has an input port. If you examine it closely, you will see that the port represents the rising edge of a signal (because we specified our trigger to be "rising edge")
- Add a sine wave input and a scope from the "sources" and "sinks" blocks in the Library Browser
- Connect them as shown. You may use the default sine wave parameters



Configuration Parameters

- From the "Simulation" menu select "Model Configuration Parameters"
- Expand the window by clicking "Solver Details"
- Specify Stop Time = 100 and choose "Fixed Step" solver "discrete (no continuous states). Specify a sample time of 0.001
- Be sure to hit "Apply" before closing the window

Solver	Simulation time	
Data Import/Export Optimization	Start time: 0.0	Stop time: 100.0
Diagnostics		
Hardware Implementation	Solver options	
Model Referencing	Type: Fixed-step	Solver: discrete (no continuous states)
Simulation Target		
Code Generation	 Additional parameters 	
	Fixed-step size (fundamental sample ti	ne): 0.001
	Tasking and sample time options	
	Periodic sample time constraint: Unco	nstrained 👻
	Treat each discrete rate as a separa	ate task
	Allow tasks to execute concurrently	on target
	Automatically handle rate transition	for data transfer
	Higher priority value indicates highe	
		r task phoney


Running the Simulation

 When you run the simulation, you should see the Power_on and Power_off states change color at each rising zero crossing of the sine wave.

Add Data to Count Transitions


- If we want to count the number of transitions from Power_on to Power_off, we need to add an output and an action to our statechart
- Go back to the "Add Inputs and Outputs" menu, but this time select "Data Output to Simulink" to add data "counter" with Sope "Output".
- Specify counter as type double, and with initial value zero

0	0			Stateflow (chart) my_switc	h/on_c	off *	
File	e Edit	View	Display	Chart Simulation Analysis	Code	Tools	Help
•	• 8	\Diamond	⇒ 4	Parse Chart	9	€K	🖉 • » 🥥 • 🛗 •
on_	off			Group & Subchart		•	:
۲	🍡 my_s	switch	▶	Add Inputs & Outputs		•	Data Input From Simulink
Q		6		Add Other Elements			Data Output To Simulink
		P	ower_on	Add Pattern In Chart Insert Pattern On Selection Save Pattern		•	Event Input From Simulink Event Output To Simulink
				Save Pattern		_	Message Input From Simulini
				Format Arrange		:	Message Output To Simulink
×				Library Link		►	
				Decomposition		•	
₽Ъ				Execution Order		-	
fx				Subchart mappings			
				Properties			
				100%			FixedStepDiscrete




Increment the Counter

- Increment the counter every time the event "Switch" occurs by placing the action "counter = counter + 1" in {curly braces} following each occurrence of "Switch."
- End the action with a semicolon inside the closing brace to prevent the value of the counter from being printed to the screen each time it is incremented



Counting the Transitions


 Add a display block from the Library Browser/Sinks menu and connect it to the data output port "counter"



Toggle a Bit

- Add a new data output "light" with
 - Initial value = 0
 - Data Type = double

- Set light = 0 in the lacksquarePower off state
- Set light = 1 in the Power on state



Data light

Description

Port: 2

\$

Variable size

× >>

0

Logging

General

light

-1

Output Data must resolve to signal object

Inherited

Name

Scope:


Size:

Complexity:

Type: double

Avoid Crossing Lines

- The output "light" is assigned Port 2 by default, and you could connect it to the scope as illustrated
- It's much better practice to keep your model readable by not crossing lines
- Change ports in the Model Explorer




Change Port Values

Base Workspace Column View: Stateflow Show Details 3 of 8 object(s) Name: light Model Workspace Mame: Scope Port Resolve Signal Data Type Size InitialValue CompiledType CompiledSize Trigger Scope: Output Port: Model Workspace Gonfiguration (Active) Embedded Coder Dictionary Iight Out 1 double -1 0 unknown Data must resolve to signal object Data must resolve to signal object			Port selection					
Model Hierarchy Contents of: my_switch/on_off (only) Filter Contents Simulink Root Base Workspace Show Details 3 of 8 object(s) Image: Contents of: my_switch/on_off General bogging Description Model Workspace Model Workspace Column View: Stateflow Show Details 3 of 8 object(s) Image: Contents of: my_switch/on_off Name: light Deta light Name: light Deta light Name: light Deta light Name: light Deta light	File Edit View Tools Add Help Image: Comparison of the state of		Explorer					
Simulink Root Base Workspace my_switch_2018a* Model Workspace Model Workspace Column View: Stateflow Show Details Model Workspace Column View: Stateflow Show Details Show Netails Sof 8 object(s) Name Column View: Stateflow Show Details Show Details Sof 8 object(s) Name Ight Name Sope Output Ight Output Switch Input 1 Switch Input 1 Switch Input 1 Name Complexity: Inherited Inherited Inherited Inherited Switch Input 1 Stateflow Switch Input 1 Inherited Inhe	Search: by Name V Name	e: 🔄 🗟 Search						
Base Workspace my_switch_2018a* Model Workspace Column View: Stateflow Model Workspace Configuration (Active) Embedded Coder Dictionary Simulink Design Verifier results Simulink Design Verifier results Configuration (Active) Embedded Coder Dictionary Switch Input 1 Counter Out 1 Counter Out 2 Counter Out 1 Counter Out 1 Counter Out 1 Counter Out 1 Counter Out 2 Counter Out 2 Counter Out 2 Counter Out 2 Counter Out 1 Counter Out 1 Counter Out 2 Counter Out 2 Counter Out 1 Counter Out 2 Counter Out 1 Counter Out 1 Counter Out 2 Counter Out 2 Counter Out 1 Counter Out 2 Counter Out 2 Counter Out 1 Counter Out 1 Counter Out 2 Counter Out 2 Counter Out 1 Counter Out 2 Counter Out	Model Hierarchy 🖉 🧖	Contents of: my_switch/on_off (only)	Filter Contents	Data light				
	 Base Workspace my_switch_2018a* my_switch* Model Workspace Configuration (Active) Embedded Coder Dictionary Simulink Design Verifier results 	Name Scope Port Resolve Signal DataType Size InitialValue Image: Scope counter Out 2 double -1 0 Image: Signal Image: Scope Out 1 double -1 0 Image: Switch Input 1 1 0 1 0	CompiledType CompiledSize Trigger Unknown Unknown Rising	Name: light Scope: Output Port: 1 Data must resolve to signal object Size: -1 Variable Size: -1 Variable Complexity: Inherited > Type: double Lock data type against Fixed-Point tools Unit (e.g., m, m/s^2, N*m): inherit				
Contents Search Results		Contents	Search Results					

Non-crossing Lines


Now the model has no crossing lines and is

easier to read.




Modeling Preferences

- Alternatively, you can make your model clearer by going to the File menu on the Simulink toolbar, select
 Simulink Preferences, then select Editor Preferences and choose "Line Hop". Your lines will do something like that shown on the right.
- You can also use this menu to change your font selection and a number of other things.



Display a Square Wave



Running the simulation shows a square wave that toggles between 0 and 1 at rising zero crossings of the sine wave

Adding Data using Model Explorer

- Suppose we want to use data defined in the Matlab workspace
- We can add data to the model using Add menu in the Model Explorer

									Model Explorer			
File Edit View Tools	Add Help											
2 🗅 🖌 🖻 📽 💥	MATLAB Variable	^М ^Р	ş 🖬 🛓	1			R 8					
Search: by Name	Simulink LookupTable				8	Sear	ch					
Model Hierarchy	Simulink Breakpoint Simulink Signal	^S	Contents	of: m	y_switch/o	on_off	(only)					
 Simulink Root Base Workspace my_switch* 	Simulink NumericType	/	n View:	State	eflow		Shov	v Details				<u>5 of </u>
Handel Works	Simulink Bus		ne		Scope	Port	Resolve Signal	DataType		Size	InitialValue	Compiled
Configuration	Simulink Variant		unter		Output	2		double		-1	0	double
Code for my_	Configuration	lig	nt		Output	1		double		-1	0	double
	Configuration Reference		wer_off wer_on									
	Message		itch		Input	1						
	🕏 Event 📕	^E										
	🐻 Data	^D										
	Trigger fx Function Call Output											
							Cont	ents	Searcl	h Res	sults	


Use a Parameter Defined in Workspace

• Add data with Name "k", Scope "parameter", and Type "double"

					Model Explorer						
File Edit View Tools Add Help)										
Search: by Name	•	Name:		∂	Search						
Model Hierarchy	8	Contents	of: my_switch/on_	off (only)		Filter Cont	ents	Data k			
 Simulink Root Base Workspace my_switch* 		Column View:	Stateflow	٢	Show Details	6 of 9 object(s)	$\overline{\gamma}$	General Description			
📊 Model Workspace 🍓 Configuration (Active)		Name	▲ Scope	Port Reso	olve Signal DataType		Size InitialValu	e Scope: Parameter 🗘 🗸			
Code for my_switch		🐻 counter	Output	2	double		-1 0				
▶		🐻 k	Parameter		double		-1	Size: -1			
	0	 light Power_off Power_on 	Output	1	double		-1 0	Complexity: Inherited 🗘			
		Switch	Input	1				Lock data type against Fixed-Point tools			
								Add to Watch Window			
				~				Revert Help Apply			
				Contents	Search Re	sults					

Model Properties

Navigate to the Menu "File/Model Properties/Model Properties"



Model Callbacks

- Navigate to "Model Properties/Callbacks/InitFcn"
- Define the value of the parameter k.

		Model Pr	operties:	my_switch		
	Main	Callbacks	History	Description	Data	
Model callba	cks	Model ini	tialization fu	nction:		
PreLoadFcn PostLoadFcn		k=-1;				
InitFcn* StartFcn PauseFcn ContinueFcn StopFcn PreSaveFcn PostSaveFcn CloseFcn						
			ОК	Cance	el He	lp Apply

Using the Parameter

Set light equal to k and run the simulation to see an inverted square wave

